# iCBD-Replication Documentation

Release 1.0.0

Luis Silva

# **ICBD REPLICATION MODULE**

1	API o	documentation	3
	1.1	icbdrep.ImageRepo module	3
	1.2	icbdrep.KeepAlive module	4
	1.3	icbdrep.MasterNode module	5
	1.4	icbdrep.NameServer module	6
	1.5	icbdrep.ReplicaNode module	6
	1.6	icbdrep.icbdrepd module	8
	1.7	lib.benchmarkinglib module	8
	1.8	lib.btrfslib module	9
	1.9	lib.compressionlib module	10
	1.10	lib.icbdSnapshot module	12
	1.11	lib.restapilib module	13
	1.12		14
	1.13	lib.sshlib module	14
	1.14	lib.utillib module	14
	1.15	exceptions.ImageRepoException module	15
	1.16	exceptions.ReplicasException module	15
	1.17	tests.benchLibTests module	15
	1.18	tests.pyroNSTests module	16
	1.19	tests.utilTests module	16
	1.20	Indices and tables	16
Ру	thon N	Module Index	17
In	dex		19

#### API DOCUMENTATION

We maintain a set of API documentation, autogenerated from the python source code's docstrings (which are typically very thorough.) and for the RESTfull API (TODO: FUTURE)

# 1.1 icbdrep.lmageRepo module

class icbdrep.ImageRepo.ImageRepo(config)

Returns: a list of strings with the images names

```
Bases: object
addImage (image_name: str)
     Add an image name to the repository And checks if in that directory are already present some snapshots
     Args: image_name: name of the image to be added
     Returns: None
     Raises: DirNotFoundException, BTRFSPathNotFoundException, ImageAlreadyExistsException
addSnapshot (image\_name: str, snap\_number: str) \rightarrow None
     Add a snapshot to a image
     Args: image_name: the name of the image to receive a snapshot snap_number: the snapshot
     Returns: None
     Raises: BTRFSSubvolumeNotFoundException, SnapshotAlreadyExistsException
deleteImage(image\_name: str) \rightarrow None
     Deletes a given image from the repository
     Args: image_name: the name of the image to be deleted
     Returns: None
     Raises: ImageNotFoundException
deleteSnapshot (image\_name: str, snap\_number: str) \rightarrow lib.icbdSnapshot.icbdSnapshot
     Deletes a given snapshot of an image
     Args: image_name: the image to which the snapshot refers to snap_number: the snapshot number
     Returns: None
     Raises: SnapshotNotFoundException
getImagelist() → typing.List[str]
     Get the list of the VM images present in the repo
```

# getImagepath (image\_name: str) → str Returns the path to the given image. Args: image\_name: the name of the image Returns: a string with the path to the image Raises: ImageNotFoundException getLastSnapshot (image\_name: str) → lib.icbdSnapshot.icbdSnapshot Get the last snapshot from the given image. Args: image\_name: name of the image Returns: an obj icbdSnapshot Raises: ImageNotFoundException

getSnapshot ( $image\_name: str, snap\_number: str$ )  $\rightarrow$  lib.icbdSnapshot.icbdSnapshot

Gets a specific snapshot given its number and the image name

**Args:** image\_name: the name of the image snap\_number: the number of the snapshot

Returns: an icbdSnapshot object

Raises: SnapshotNotFoundException

 $\texttt{getSnapshotlist} (\textit{image\_name}: \textit{str}) \rightarrow \texttt{typing.List} [\texttt{lib.icbdSnapshot.icbdSnapshot}]$ 

Get the list of snapshots present in the repo for the given image. If there are no snapshots it returns a empty list.

**Args:** image\_name: The image name that contains the snapshots

Returns: a list with the snapshots present in the repo

Raises: Image Not Found Exception

 $hasImage(image\_name: str) \rightarrow bool$ 

Check if a given image name is present in the repository

Args: image\_name: the image name to be checked

Returns: True if present, otherwise False

 $\textbf{hasSnapshot} \ (\textit{image\_name: str}, \textit{snap\_number: str}) \ \rightarrow \textbf{bool}$ 

Check if a snapshot is present in the given image

Args: image\_name: the name of the image that should contain the snapshot snap\_number: the snapshot

Returns: True if the snapshot is present, otherwise False

# 1.2 icbdrep.KeepAlive module

**Args:** pyro\_bind: boolean True to use of the \_pyroBind or False to use the ping method

Returns: None

run()

The main method of the class. This is triggered in the thread.start() call

Returns: None

 $stopKeepAlive() \rightarrow None$ 

Stop the execution of the keep alive thread. This should be part of the shutdown process.

Returns: None

# 1.3 icbdrep.MasterNode module

```
class icbdrep.MasterNode.MasterNode (node_config, ns_config, interactive_mode_flag: bool)
    Bases: threading.Thread
```

 $\mathbf{addImage} \ (\mathit{image\_name} \colon \mathit{str}, \mathit{node} \colon \mathit{int}) \ \to \mathsf{None}$ 

Add an image to the node repository

Args: image\_name: the name of the image to be added node: the node where the image will be added

Returns: Node

 $delete\_snapshot(image\_name: str, snap\_number: str, node: int) \rightarrow None$ 

Deletes a snapshot from a given image in a node.

**Args:** image\_name: the image name snap\_number: the snapshot number node: the node to do the deletion

Returns: None

**exeCommand** (line: str)  $\rightarrow$  None

Receives a command line and interprets the content. Separating the various fields of the string into arguments, and calls the appropriated function.

**Args:** line: a line with the command to execute

Returns: None

getReplicasFromNS() -> (<class 'int'>, typing.Dict[int, Pyro4.core.Proxy])

Get a list of the replicas present in the system (Name Server) and saves them to the replicas proxy list

Returns: the number of found replicas

 $\textbf{interactiveMode} \, (\,) \, \to None$ 

When in interactive mode, the server runs with a prompt, so that individual commands can be typed in

Returns: None

 $listImages(node: int) \rightarrow None$ 

List the collection of images available in a node.

Args: node: The node to list. (Master or one of the Replicas)

Returns: None

 $\textbf{listReplicas}\,()\,\to None$ 

List the replicas present in the system and prints to the console.

Returns: None

listSnapshots (node: int, image\_name: str)  $\rightarrow$  None

List the colection of snapshots of a given image in a node.

**Args:** node: The node to list (Master or one of the replicas) image\_name: The image the snapshots refer to

```
Returns: None

registerInNS () → Pyro4.core.Daemon
Register the server in the Name Server
Returns: the registered daemon

run ()
The main method of the class. This is triggered in the thread.start() call
Returns: None

send (node: int, image_name: str, snapshot_number: str, blocking: bool, ssh: bool = False, compression: str = None) → None
Send Command - Instructs the replica to listen for a transfer, and sends the snapshot in the btrfs path

Args: node: the number of the node image_name: the name of the image snapshot_number: the number of the image blocking: if the function should block
Returns: None

stopMaster() → None
WARNING!! Don't use this! Only for testing and should be deprecated!
Returns: None
```

# 1.4 icbdrep.NameServer module

```
class icbdrep.NameServer.NameServer(config)
    Bases: threading.Thread

run()
    The main method of the class. This is triggered in the thread.start() call
    Returns: None

stopNS() → None
    This function closes both the broadcast and name servers. This is called in the shutdown procedure.
    Returns: None
```

# 1.5 icbdrep.ReplicaNode module

```
class icbdrep.ReplicaNode.ReplicaNode(rep_id: int, node_config, ns_config)
Bases: object

addImage(image_name: str) → bool
   Add an image to the node's repository

Args: image_name: the name of the image to be added.

Returns: a boolean with the sucess of the operation

deleteSnapshot(image_name: str, snap_number: str) → lib.icbdSnapshot.icbdSnapshot
   Delete a snapshot from the repo and FS

Args: image_name: the name of the image snap_number: the number of the snapshot
   Returns: the snapshot which as deleted
```

#### $getImagesList() \rightarrow typing.List[str]$

Get the list of images present in the replica

Returns: a list of strings

#### getLastSnapshot ( $image\_name: str$ ) $\rightarrow$ lib.icbdSnapshot.icbdSnapshot

Return the last snapshot of the given image.

**Args:** image\_name: the name of the image

Returns: an obj icbdSnapshot

#### $\texttt{getName}() \rightarrow str$

Get the replica name

Returns: a string with the name

#### **getReplicaBtrfsAddress**() → typing.Tuple[str, int]

Return the IP and PORT address for the btrfs transfer.

Returns: A tuple with an IP and PORT

#### $getReplicaID() \rightarrow int$

Get the replica ID number. This should be a integer that originates from the

Returns: the replica ID

#### $\texttt{getSnapshotList} (image\_name: str) \rightarrow \texttt{typing.List} [lib.icbdSnapshot.icbdSnapshot]$

Return the list of snapshots stored in the repo for the given image name. Case there are no snapshots the list returned is empty. Case the image in args ins't in the repo return None.

Args: image\_name: Image name to get the snapshot list.

Returns: a list with the snapshots.

#### $ping() \rightarrow str$

Responds to a ping request with "pong"

Returns: "pong"

#### $poisonPill() \rightarrow None$

Shutdown message to the replica

Returns: None

#### **prepareReceive** ( $image\_name: str, snap\_number: str) \rightarrow bool$

This function should precede the receive() call. Checks if the node wants the image in question or if the snapshot is already present.

**Args:** image name: the name of the image snap number: the name of the snap

Returns: a bool that indicates if the replica will accept the receive

**receive** (*image\_name*: *str*, *snap\_number*: *str*, *compression*: *str* = *None*)

Receives a snapshot

Returns: None

# 1.6 icbdrep.icbdrepd module

# 1.7 lib.benchmarkinglib module

```
class lib.benchmarkinglib.Benchmark(name)
     Bases: object
     addRun (run: lib.benchmarkinglib.Run)
     get_name()
     mean()
     median()
     stdev()
class lib.benchmarkinglib.Run (interfaceName, runNumber=-1, imageName='default')
     Bases: object
     getBtrfsTransferBytes()
         Returns:
     getBtrfsTransferPackets()
         Returns:
     getBtrfsTransferRuntime()
         Returns:
     getGlobalTransferRuntime()
         Returns:
     getIcbdBootTransferBytes()
         Returns:
     getIcbdBootTransferPackets()
         Returns:
     getIcbdBootTransferRuntime()
         Returns:
     getIscsiTargetTransferBytes()
         Returns:
     getIscsiTargetTransferPackets()
     getIscsiTargetTransferRuntime()
         Returns:
     startTimmer (transferType)
         Start a timmer for one of the transfer counters.
         Args: transferType: the type of the transfer to start counting time
         Returns: call the appropriated function
     stopTimmer (transferType)
         Stop a timmer for one of the transfer counters.
         Args: transferType: the type of the transfer to start counting time
         Returns: call the appropriated function
```

#### class lib.benchmarkinglib.linuxNetworkTraffic

Bases: object

#### static getInterfaceStats(interfaceName)

**Args:** interfaceName:

Returns:

#### 1.8 lib.btrfslib module

#### class lib.btrfslib.BtrfsFsCheck

Bases: object

#### static isBtrfsPath(path: str)

Check if a given path is in fact present in a BTRFS tree

!!Caution!!: This function does not takes into account the fact that the path might not be a valid one.

**Args:** path: the path to be checked

Returns: true if present, otherwise falses

#### static isBtrfsSubvolume(path: str)

Check if the given path is a BTRFS subvolume / snapshot.

**Args:** path: the path to be checked

Returns: True if a subvolume, otherwise false

#### static searchForSnapshots(path: str) → typing.List[str]

Search the directory, and gets the snapshots that are already present

**Args:** path: the directory to be searched

Returns: a List with the name of the snapshot

#### class lib.btrfslib.BtrfsTool

Bases: object

#### static delete (path: str) $\rightarrow$ None

Wrapper for the BTRFS Tools subvolume delete command.

The method receives a path and calls the btrfs subvolume delete for that path.

**Args:** path: the path to the subvolume to delete

Returns: None

#### static receive (dst\_path: str, src\_port: int, compression: str = None)

Wrapper for the BTRFS Tools receive() command.

This method opens a socket and listens for a connection Then receives a snapshot and redirect it to the stdin of the BTRFS receive

**Args:** dst\_path: the path of the image to place the snapshot src\_port: the port to listening for the transfer

Returns: None

## $\textbf{static send} \ (\textit{src\_path: str}, \textit{dst\_ip: str}, \textit{dst\_port: int, parent: str} = \textit{None}, \textit{compression: str} = \textit{None})$

Wrapper for the BTRFS Tools send() command.

This method is BLOCKING, it will wait for the conclusion of the send command. It uses regular sockets to send to an endpoint the data from the snapshot.

1.8. lib.btrfslib module 9

**Args:** src\_path: the path of the snapshot to be send dst\_ip: the IP of the destiny socket dst\_port: the Port the destiny is listening

Returns: None

Wrapper for the BTRFS Tools send() command.

This method is NON BLOCKING, it will NOT wait for the conclusion of the send command. It uses regular sockets to send to an endpoint the data from the snapshot.

**Args:** src\_path: the path of the snapshot to be send dst\_ip: the IP of the destiny socket dst\_port: the Port the destiny is listening

Returns: None

**static sendSSH** ( $src\_path$ : str,  $dst\_ip$ : str,  $dst\_port$ : int, parent: str = None, compression: str = None)

Wrapper for the BTRFS Tools send() command.

This method is BLOCKING, it will wait for the conclusion of the send command. It uses regular sockets to send to an endpoint the data from the snapshot.

**Args:** src\_path: the path of the snapshot to be send dst\_ip: the IP of the destiny socket dst\_port: the Port the destiny is listening

Returns: None

 $static setReadOnly(path: str, state: bool) \rightarrow None$ 

Wrapper for the BTRFS Tools property set read only command.

This method sets the tread only property for the given subvolume in the path.

Args: path: the path to the subvolume state: a boolean of the state of the read only

Returns: None

# 1.9 lib.compressionlib module

class lib.compressionlib.compressionLib

Bases: object

 $static checkCompression(compression: str) \rightarrow bool$ 

Check if the given compression algorithm is available to use in the lib.

**Args:** compression: A string with the algorithm to check

Returns: A bool representing the availability of the chosen algo.

class lib.compressionlib.g\_snappy

Bases: object

static compressStream (in\_stream, out\_stream, blocksize=65536) → None

Uses the Google snappy compress function to compress a stream of bytes.

Takes an incoming file-like object and an outgoing file-like object, reads data from "in\_stream", compresses it, and writes it to "out\_stream" should support the read method, and "out\_stream" should support the write method.

**Args:** in\_stream: a stream of bytes out\_stream: a compressed stream blocksize: [optional] the size used for the buffer in bytes

Returns: None

#### $static compress\_native(in\_stream, out\_stream, blocksize=65536) \rightarrow None$

Wrapper for the snappy native stream compression

**Args:** in\_stream: a stream of bytes out\_stream: a compressed stream blocksize: [optional] the size used for the buffer in bytes

Returns:

#### static decompressStream (in\_stream, out\_stream, blocksize=65536) → None

Uses the Google snappy decompress function to handle a compressed stream.

Takes an incoming file-like object and an outgoing file-like object, reads data from "in\_stream", decompresses it, and writes it to "out\_stream" should support the read method, and "out\_stream" should support the write method.

**Args:** in\_stream: a compressed stream out\_stream: the original stream of bytes blocksize: [optional] the size used for the buffer in bytes

Returns:None

#### static decompress\_native(in\_stream, out\_stream, blocksize=65536) → None

Wrapper for the snappy native stream decompression

**Args:** in\_stream: a compressed stream out\_stream: the original stream of bytes blocksize: [optional] the size used for the buffer in bytes

Returns:

#### class lib.compressionlib.lz4

Bases: object

#### $static compressStream(in\_stream, out\_stream) \rightarrow None$

Uses the lz4 compress function to compress a stream of bytes

Takes an incoming file-like object and an outgoing file-like object, reads data from "in\_stream", compresses it, and writes it to "out\_stream" should support the read method, and "out\_stream" should support the write method.

Args: in\_stream: a bytes input stream to be compressed out\_stream: the compressed stream

Returns: None

#### $static decompressStream(in\_stream, out\_stream) \rightarrow None$

Uses the lz4 decompress function to decompress a stream of bytes

Takes an incoming file-like object and an outgoing file-like object, reads data from "in\_stream", decompresses it, and writes it to "out\_stream" should support the read method, and "out\_stream" should support the write method.

Args: in\_stream: a compressed stream out\_stream: the original bytes

Returns: None

#### class lib.compressionlib.z\_lib

Bases: object

# static compress2 (in\_stream, out\_stream)

!!IN TESTING!! !!DONT USE THIS!!

**Args:** in\_stream: out\_stream:

Returns:

```
static compressStream (in_stream, out_stream, blocksize=32768) \rightarrow None
```

Uses the zlib compress function to compress a stream of bytes.

Takes an incoming file-like object and an outgoing file-like object, reads data from "in\_stream", compresses it, and writes it to "out\_stream". "in\_stream" should support the read method, and "out\_stream" should support the write method.

**Args:** in\_stream: a stream of bytes out\_stream: a compressed stream blocksize: [optional] the size used for the buffer in bytes

Returns: None

#### static decompress2 (in\_stream, out\_stream)

!!IN TESTING!! !!DONT USE THIS!!

**Args:** in\_stream: out\_stream:

Returns:

#### $static decompressStream (in\_stream, out\_stream, blocksize=32768) \rightarrow None$

Uses the zlib decompress function to handle a compressed stream.

Takes an incoming file-like object and an outgoing file-like object, reads data from "in\_stream", decompresses it, and writes it to "out\_stream" should support the read method, and "out\_stream" should support the write method.

**Args:** in\_stream: a compressed stream out\_stream: the original stream of bytes blocksize: [optional] the size used for the buffer in bytes

Returns: None

# 1.10 lib.icbdSnapshot module

Bases: object

#### getICBDBootPackagePath()

Get a string with the full path to the iCBD Boot Package of the Image.

Returns: a string with the path

#### getISCSITarget()

Get a string with the path to the ISCSI target for this snapshot.

Returns: a string with the path

#### $\texttt{getImagePath}\,(\,)\,\to str$

Get a string with the formatted path, but without the snapshot number. This should be used as a destiny path

Returns: a string with the path in the format {/mountpoint/imagename}

#### $\texttt{getMountpointPath}\,(\,)\,\to str$

Get a string with only the mount point of the snapshot

Returns: the mountpoint

#### $getPath() \rightarrow str$

Get a string with the full path of the snapshot, including the mountpoint and image name. Format: {mountpoint/imagename/snapshotnumber}

Returns: a string with the path

# 1.11 lib.restapilib module

```
class lib.restapilib.RestAPI (port: int = 5009)
```

Bases: object

iCBD-Replication Rest API Class

This instantiate the micro-framework Flack to provide a simple HTTP API for interacting with the system.

Note that every communication with this API uses JSON files. Responses are in JSON and an example can be found in the documentation of each method.

```
api = <flask_restful.Api object>
app = <Flask 'lib.restapilib'>
```

#### deleteImageVersion (replica, imi, version)

Delete a version of an iMI in a Replica Json response example:

Endpoint path: <IP>:<Port>/api/replicas/<replica>/imis/<imi>/versions/<version>/delete/

Returns:

#### listImageVersionsByReplica (replica, imi)

List the version of an iMI that are present in a Replica Json response example:

Endpoint path : <IP>:<Port>/api/replicas/<replica>/imis/<imi>/versions

Returns:

#### listImagesByReplica(replica)

List all iMIS present in a replica. Json response example:

Endpoint path : <IP>:<Port>/api/replicas/<replica>/imis

Returns:

#### listReplicas()

List all the replicas registered in the system. Json response example:

Endpoint path : <IP>:<Port>/api/replicas

Returns:

#### listSystemImages()

List all the iMIs present in the Master Node This will list all iMIs available to be transferred to any replica.

Json response example:

Endpoint path : <IP>:<Port>/api/master/imis

Returns:

#### listSystemImagesVersions (imi)

List all the versions of an iMIs present in the Master Node

Json response example:

Endpoint path : <IP>:<Port>/api/master/imis/<imi>/versions

Returns:

```
root()
     Default root route endpoint. Mainly for testing
     Endpoint path: <IP>:<Port>/api
     Returns: a simple test string
sendImageVersionToReplica()
     List all the versions of an iMIs present in the Master Node
     Json response example:
     Endpoint path: <IP>:<Port>/api/master/send?imi={imi}&version={version}&replica={replica}
     Returns:
subscribeImage (replica, imi)
     Replica subscribe to a iMI Json response example:
     Endpoint path: <IP>:<Port>/api/replicas/<replica>/imis/subscribe/<imi>
     Returns:
unsubscribeImage (replica, imi)
     Replica unsubscribe to a iMI Json response example:
     Endpoint path: <IP>:<Port>/api/replicas/<replica>/imis/unsubscribe/<imi>
     Returns:
```

#### 1.12 lib.serializerslib module

```
class lib.serializerslib.icbdSnapshotSerializer
    Bases: object
    static icbdSnapshot_class_to_dict(obj: lib.icbdSnapshot.icbdSnapshot)
    static icbdSnapshot_dict_to_class(class_name, dict)
```

#### 1.13 lib.sshlib module

```
class lib.sshlib.sshTunnel(host, local_port, remote_port)
    Bases: object
    createTunnel(host, local_port, remote_port)
```

#### 1.14 lib.utillib module

```
class lib.utillib.icbdUtil
Bases: object
logHeading (string)
Big header for logger -[ "string" ]———
Args: string: a string to be placed inside the big header
Returns: the string encapsulated in the header
```

prettify(obj)

Return pretty representation of obj. Useful for debugging.

**Args:** obj: the object to prettify

Returns: a pretty representation of obj

# 1.15 exceptions.ImageRepoException module

exception exceptions.ImageRepoException.BTRFSPathNotFoundException(message)

Bases: Exception

Raise when a BTRFS Path is not in the File System

exception exceptions.ImageRepoException.BTRFSSubvolumeNotFoundException (message)

Bases: Exception

Raise when a BTRFS Subvolume is not in the File System

exception exceptions.ImageRepoException.DirNotFoundException (message)

Bases: Exception

Raise when a Directory is not in the File System

**exception** exceptions.ImageRepoException.ImageAlreadyExistsException (message)

Bases: Exception

Raise when a Images already is present in the repo

**exception** exceptions.ImageRepoException.ImageNotFoundException (message)

Bases: Exception

Raise when a Images is not found

exception exceptions.ImageRepoException.SnapshotAlreadyExistsException (message)

Bases: Exception

Raise when a Snapshot already is present in the repo

 $\textbf{exception} \ \texttt{exceptions.} \\ \textbf{ImageRepoException.} \\ \textbf{SnapshotNotFoundException} \ (\textit{message})$ 

Bases: Exception

Raise when a Snapshot is not found

# 1.16 exceptions.ReplicasException module

exception exceptions.ReplicasException.ReplicaNotFoundException (message)

Bases: Exception

Raise when a replica is not found

## 1.17 tests.benchLibTests module

```
tests.benchLibTests.dummyFunc()
tests.benchLibTests.main()
tests.benchLibTests.startCompleteRun()
```

# 1.18 tests.pyroNSTests module

```
class tests.pyroNSTests.NamingTrasher(nsuri, number)
    Bases: threading.Thread
    list()
    listprefix()
    listregex()
    lookup()
    register()
    remove()
    run()

tests.pyroNSTests.main()
tests.pyroNSTests.randomname()
```

## 1.19 tests.utilTests module

```
class tests.utilTests.TestMount (methodName='runTest')
    Bases: unittest.case.TestCase
    Our basic test class
    isBTRFS (path, assertVal)
    isSubvolume (path, assertVal)
    test_isBtrfsSet()
    test_isSubvolumeSet()
```

## 1.20 Indices and tables

- genindex
- · modindex
- · search

# **PYTHON MODULE INDEX**

```
е
exceptions.ImageRepoException, 15
{\tt exceptions.ReplicasException, 15}
icbdrep.ImageRepo, 3
icbdrep.KeepAlive, 4
icbdrep.MasterNode, 5
icbdrep.NameServer,6
icbdrep.ReplicaNode, 6
lib.benchmarkinglib, 8
lib.btrfslib,9
lib.compressionlib, 10
lib.icbdSnapshot, 12
lib.restapilib, 13
lib.serializerslib, 14
lib.sshlib, 14
lib.utillib, 14
tests.benchLibTests, 15
tests.pyroNSTests, 16
tests.utilTests, 16
```

18 Python Module Index

# **INDEX**

Α	decompressStream() (lib.compressionlib.lz4 static
addImage() (icbdrep.ImageRepo.ImageRepo method), 3 addImage() (icbdrep.MasterNode.MasterNode method),	method), 11 decompressStream() (lib.compressionlib.z_lib static method), 12
addImage() (icbdrep.ReplicaNode.ReplicaNode method),	delete() (lib.btrfslib.BtrfsTool static method), 9 delete_snapshot() (icbdrep.MasterNode.MasterNode
addRun() (lib.benchmarkinglib.Benchmark method), 8 addSnapshot() (icbdrep.ImageRepo.ImageRepo method),	method), 5 deleteImage() (icbdrep.ImageRepo.ImageRepo method), 3
api (lib.restapilib.RestAPI attribute), 13 app (lib.restapilib.RestAPI attribute), 13	deleteImageVersion() (lib.restapilib.RestAPI method), 13 deleteSnapshot() (icbdrep.ImageRepo.ImageRepo
Benchmark (class in lib.benchmarkinglib), 8	method), 3 deleteSnapshot() (icbdrep.ReplicaNode.ReplicaNode method), 6
BtrfsFsCheck (class in lib.btrfslib), 9 BTRFSPathNotFoundException, 15	DirNotFoundException, 15 dummyFunc() (in module tests.benchLibTests), 15
BTRFSSubvolumeNotFoundException, 15 BtrfsTool (class in lib.btrfslib), 9	E L. D. F ( 11) 45
С	exceptions.ImageRepoException (module), 15 exceptions.ReplicasException (module), 15
checkCompression() (lib.compressionlib.compressionLib static method), 10	exeCommand() (icbdrep.MasterNode.MasterNode method), 5
compress2() (lib.compressionlib.z_lib static method), 11 compress_native() (lib.compressionlib.g_snappy static	G
method), 11 compressionLib (class in lib.compressionlib), 10	g_snappy (class in lib.compressionlib), 10 get_name() (lib.benchmarkinglib.Benchmark method), 8
compressStream() (lib.compressionlib.g_snappy static method), 10	getBtrfsTransferBytes() (lib.benchmarkinglib.Run method), 8
compressStream() (lib.compressionlib.lz4 static method),	getBtrfsTransferPackets() (lib.benchmarkinglib.Run method), 8
compressStream() (lib.compressionlib.z_lib static method), 11	getBtrfsTransferRuntime() (lib.benchmarkinglib.Run method), 8
createTunnel() (lib.sshlib.sshTunnel method), 14	getGlobalTransferRuntime() (lib.benchmarkinglib.Run method), 8
D decompress2() (lib.compressionlib.z_lib static method),	getICBDBootPackagePath() (lib.icbdSnapshot.icbdSnapshot method), 12
decompress_native() (lib.compressionlib.g_snappy static	getIcbdBootTransferBytes() (lib.benchmarkinglib.Run method), 8
method), 11 decompressStream() (lib.compressionlib.g_snappy static method), 11	getIcbdBootTransferPackets() (lib.benchmarkinglib.Run method), 8

getIcbdBootTransferRuntime() (lib.benchmarkinglib.Run method), 8	<pre>icbdSnapshot (class in lib.icbdSnapshot), 12 icbdSnapshot_class_to_dict()</pre>
getImagelist() (icbdrep.ImageRepo.ImageRepo method), 3	(lib.serializerslib.icbdSnapshotSerializer static method), 14
getImagepath() (icbdrep.ImageRepo.ImageRepo	icbdSnapshot_dict_to_class()
method), 3	(lib.serializerslib.icbdSnapshotSerializer
getImagePath() (lib.icbdSnapshot.icbdSnapshot method),	static method), 14
12	icbdSnapshotSerializer (class in lib.serializerslib), 14
getImagesList() (icbdrep.ReplicaNode.ReplicaNode	icbdUtil (class in lib.utillib), 14
method), 6	ImageAlreadyExistsException, 15
getInterfaceStats() (lib.benchmarkinglib.linuxNetworkTraff	
static method), 9	
· · · · · · · · · · · · · · · · · · ·	ImageRepo (class in icbdrep.ImageRepo), 3
getISCSITarget() (lib.icbdSnapshot.icbdSnapshot	interactiveMode() (icbdrep.MasterNode.MasterNode
method), 12	method), 5
getIscsiTargetTransferBytes() (lib.benchmarkinglib.Run	isBTRFS() (tests.utilTests.TestMount method), 16
method), 8	isBtrfsPath() (lib.btrfslib.BtrfsFsCheck static method), 9
getIscsiTargetTransferPackets()	isBtrfsSubvolume() (lib.btrfslib.BtrfsFsCheck static
(lib.benchmarkinglib.Run method), 8	method), 9
getIscsiTargetTransferRuntime()	isSubvolume() (tests.utilTests.TestMount method), 16
(lib.benchmarkinglib.Run method), 8	V
getLastSnapshot() (icbdrep.ImageRepo.ImageRepo	K
method), 4	KeepAlive (class in icbdrep.KeepAlive), 4
$getLastSnapshot() \\ \hspace{0.5cm} (icbdrep.ReplicaNode.ReplicaNode$	keepAlive() (icbdrep.KeepAlive.KeepAlive method), 4
method), 7	
getMountpointPath() (lib.icbdSnapshot.icbdSnapshot	L
method), 12	lib.benchmarkinglib (module), 8
getName() (icbdrep.ReplicaNode.ReplicaNode method),	lib.btrfslib (module), 9
7	lib.compressionlib (module), 10
getPath() (lib.icbdSnapshot.icbdSnapshot method), 12	lib.icbdSnapshot (module), 12
getReplicaBtrfsAddress() (icb-	lib.restapilib (module), 13
drep.ReplicaNode.ReplicaNode method),	lib.serializerslib (module), 14
7	lib.sshlib (module), 14
getReplicaID() (icbdrep.ReplicaNode.ReplicaNode	lib.utillib (module), 14
method), 7	
getReplicasFromNS() (icbdrep.MasterNode.MasterNode	linuxNetworkTraffic (class in lib.benchmarkinglib), 8
method), 5	list() (tests.pyroNSTests.NamingTrasher method), 16
getSnapshot() (icbdrep.ImageRepo.ImageRepo method),	listImages() (icbdrep.MasterNode.MasterNode method),
4	5
getSnapshotlist() (icbdrep.ImageRepo.ImageRepo	listImagesByReplica()  (lib.restapilib.RestAPI  method),
method), 4	13
getSnapshotList() (icbdrep.ReplicaNode.ReplicaNode	listImageVersionsByReplica() (lib.restapilib.RestAPI
method), 7	method), 13
memody, 7	listprefix() (tests.pyroNSTests.NamingTrasher method),
H	16
	listregex() (tests.pyroNSTests.NamingTrasher method),
hasImage() (icbdrep.ImageRepo.ImageRepo method), 4	16
hasSnapshot() (icbdrep.ImageRepo.ImageRepo method),	listReplicas() (icbdrep.MasterNode.MasterNode
4	method), 5
I	listReplicas() (lib.restapilib.RestAPI method), 13
1	listSnapshots() (icbdrep.MasterNode.MasterNode
icbdrep.ImageRepo (module), 3	method), 5
icbdrep.KeepAlive (module), 4	listSystemImages() (lib.restapilib.RestAPI method), 13
icbdrep.MasterNode (module), 5	listSystemImagesVersions() (lib.restapilib.RestAPI
icbdrep.NameServer (module), 6	method), 13
icbdrep.ReplicaNode (module), 6	logHeading() (lib.utillib.icbdUtil method), 14

20 Index

lookup() (tests.pyroNSTests.NamingTrasher method), 16 startCompleteRun() (in module tests.benchLibTests), 15 lz4 (class in lib.compressionlib), 11 startTimmer() (lib.benchmarkinglib.Run method), 8 stdev() (lib.benchmarkinglib.Benchmark method), 8 M stopKeepAlive() (icbdrep.KeepAlive.KeepAlive method), main() (in module tests.benchLibTests), 15 stopMaster() (icbdrep.MasterNode.MasterNode method), main() (in module tests.pyroNSTests), 16 MasterNode (class in icbdrep.MasterNode), 5 stopNS() (icbdrep.NameServer.NameServer method), 6 mean() (lib.benchmarkinglib.Benchmark method), 8 stopTimmer() (lib.benchmarkinglib.Run method), 8 median() (lib.benchmarkinglib.Benchmark method), 8 subscribeImage() (lib.restapilib.RestAPI method), 14 Ν NameServer (class in icbdrep.NameServer), 6 test\_isBtrfsSet() (tests.utilTests.TestMount method), 16 NamingTrasher (class in tests.pyroNSTests), 16 test\_isSubvolumeSet() (tests.utilTests.TestMount method), 16 TestMount (class in tests.utilTests), 16 ping() (icbdrep.ReplicaNode.ReplicaNode method), 7 tests.benchLibTests (module), 15 poisonPill() (icbdrep.ReplicaNode.ReplicaNode method), tests.pyroNSTests (module), 16 tests.utilTests (module), 16 prepareReceive() (icbdrep.ReplicaNode.ReplicaNode method), 7 U prettify() (lib.utillib.icbdUtil method), 14 unsubscribeImage() (lib.restapilib.RestAPI method), 14 R Ζ randomname() (in module tests.pyroNSTests), 16 z\_lib (class in lib.compressionlib), 11 receive() (icbdrep.ReplicaNode.ReplicaNode method), 7 receive() (lib.btrfslib.BtrfsTool static method), 9 register() (tests.pyroNSTests.NamingTrasher method), 16 registerInNS() (icbdrep.MasterNode.MasterNode method), 6 remove() (tests.pyroNSTests.NamingTrasher method), 16 ReplicaNode (class in icbdrep.ReplicaNode), 6 ReplicaNotFoundException, 15 RestAPI (class in lib.restapilib), 13 root() (lib.restapilib.RestAPI method), 13 Run (class in lib.benchmarkinglib), 8 run() (icbdrep.KeepAlive.KeepAlive method), 4 run() (icbdrep.MasterNode.MasterNode method), 6 run() (icbdrep.NameServer.NameServer method), 6 run() (tests.pyroNSTests.NamingTrasher method), 16 searchForSnapshots() (lib.btrfslib.BtrfsFsCheck static method), 9 send() (icbdrep.MasterNode.MasterNode method), 6 send() (lib.btrfslib.BtrfsTool static method), 9 sendImageVersionToReplica() (lib.restapilib.RestAPI method), 14 sendNonBlock() (lib.btrfslib.BtrfsTool static method), 10 sendSSH() (lib.btrfslib.BtrfsTool static method), 10 setReadOnly() (lib.btrfslib.BtrfsTool static method), 10 SnapshotAlreadyExistsException, 15 SnapshotNotFoundException, 15 sshTunnel (class in lib.sshlib), 14

Index 21